

mapesen

Face Recognition Access Control
Temperature Thermal Scanner CMS
Quick User Instructions


www.mapesen.com

1. Sign in

Double click the CMS icon,open the software login interface,input the default user name and password as following.

User name admin


password 123456




The screenshot shows a 'Login' dialog box with a close button (X) in the top right corner. It contains two input fields: 'Username:' with the value 'admin' and 'Password:' with the value '123456'. Below the input fields are two buttons: 'OK' and 'Change password'.

2. Client main interface


“Click OK”,enter into the main interface as below pic:






3. Add device

3-1. Click on "Device".





3-2. Click to add.




3-3. Select the search method (search lasts about 3 seconds).



3-4. After search out the IP address of the device, check the device you want to add, click "Add the selected", the page will return to the previous page and display the added device, as shown below.




3-5. Close the add page to return to the main interface, and the device will be displayed in the device list.



4. Video viewing and face recognition

Click the connect button for video viewing and face recognition




Note: For face recognition, you need to synchronize the face database in the “detailed” first, otherwise the right face database will be blank.


5. Device Configuration

Click "detailed" to enter the page of device management interface, including face database management, attendance and visitor record export and parameter setting, please refer to the user manual of the device PC client software.

5-1. Face database management







5-2. Export of attendance records



ID	Name	time	Temperature	Mask	Event description
007	YE	2020-07-22 08:54:42	36.1°C	No	Recognized and Passed
008	Anny	2020-07-22 08:56:03	36.8°C	No	Recognized and Passed
008	Anny	2020-07-22 08:56:13	35.9°C	No	Recognized and Passed
007	YE	2020-07-22 08:59:56	35.9°C	No	Recognized and Passed
007	YE	2020-07-22 09:00:02	36.0°C	No	Recognized and Passed
008	Anny	2020-07-22 09:00:13	36.2°C	No	Recognized and Passed
007	YE	2020-07-22 09:00:20	36.2°C	No	Recognized and Passed
008	Anny	2020-07-22 09:00:24	35.9°C	No	Recognized and Passed
007	YE	2020-07-22 09:00:35	35.9°C	No	Recognized and Passed

5-3. Export of visitor record



ID	Name	time	Temperature	Mask	Snap
	visitor	2020-07-22 14:49:28	36.0°C	No	
	visitor	2020-07-22 14:49:12	36.0°C	No	
	visitor	2020-07-22 14:48:23	36.1°C	No	

5-4. Parameter settings

042067058230

Capturing interval(s):	3	TEMP detection switch:	open	Overlay time:
Snap picture quality parameters(0-1):	0.70	TEMP related relay:	Relation	On-off state of relay:
Blur parameter(0-1):	0.30	Temperature detection voice broadcast:	No broadcasting	Temperature measuring sce
Living-body threshold(0-1):	0.20	Temperature mode:	Centigrade	IO output mode:
Face recognition (0-100):	70.00	Normal TEMP threshold:	37.30	Face recognition Mode:
Identified Times (1-10):	3	Black and white list comparison switch:	open	Refresh Save
Recognition distance threshold:	1m	Face recognition associated relay:	Relation	
Face exposure threshold (0-100):	50	Face Recognition voice broadcast:	Broadcasting	
Software version:	1	Mask detection switch:	open	
Temperature compensation coefficient:	0.00	Mask detection mode:	Epidemic mode	
Qualtech, Alatau Kinnar	2	Mask associated relay:	Unrelated	

mapesen

Smart City, Smart Guarantee

MAPESEN TECHNOLOGY LIMITED

www.mapesen.com

0086(755)-89345865

info@mapesen.com